Reverse DNS lookup

If you want to see IP Address, instead of its resolved host name, you can disable reverse DNS lookup.

To enable/disable Reverse DNS lookup for IP Addresses:

- Go to blocked URL> Settings > NetFlow Settings > Configuration > Reverse DNS lookup
 Select Enabled/Disabled

Patterns Subnets Subnet Sets End Users T	opN Alarms Reports	Aggregator Filtering Sampling	Configuration
Timport A Export			
Service options			
NetFlow Collection port LDP port number listening for NetFlow date	2060		
NetFlow Collection port timeout Time before retrying latening for NetFlow UDP packets	5	seconds	
SFlow Collection port UDP port number listening for SFlow data	6344		
SFlow Collection port timeout Time before retrying latening for SFlow UDP packets	5	seconds	
End users collection port LOP port number listening for user logon/logoff syslog messages	33516		
End users collection port timeout Time before retrying listening for syslog UDP packets	5	seconds	
Temp folder Folder in which Nethbura-Flow will temporary unpack Raw Data files	/var/lib/netvizura/flow/temp		
Archived files folder Folder in which NetVoura-Flow Apprepator stores processed files	/var/lib/netvizura/flow/archive		
Legacy raw files folder Folder in which Nethburg-Flow stores Raw Data files from previous versions	/var/lib/netvizura/flow/legacy		
Maximum database size Oldes data will be removed first	10	GB	
Minimum free disk space When free space on the Raw Data storage is less than configured oldest files will be remove	4096	MB	
Database size in weeks The system will men you before database space runs out	5		
Minimum archive size in days The system will men you up to 7 days before archive space runs out	5		
Automatic Deduplication If enabled, form that have known exporter as next hop will not be processed	Enabled T		
Whois lookup If duabled, Whois kokup will be aligned for All Traffic Internal Addresses	Enabled T		
Reverse DNS lookup If duabled, Reverse DNS lookup will be sliped for all addresses	Enabled Tradided		
Save X Cancel	Disabled		

Once you change status of Reverse DNS in Settings from Enabled to Disabled \odot and vice versa, it is necessary to refresh the observed view in NetFlow module by pressing the Refresh button in the upper right corner.

Enabled is default value. (i)